

Agricultural Nutrient Management Program
Department of Environmental Science and Technology
0116 Symons Hall
7998 Regents Dr.
College Park, MD 20742
TEL 301-405-1319 | FAX 301-314-7375
www.extension.umd.edu/anmp

## Using Google Earth Pro for making maps for Nutrient Management Plans (when no P-Risk assessments are required)

#### Introduction

Google Earth Pro is a free program that can be downloaded to your desktop and can assist you in generating maps for a Maryland Nutrient Management Plan. The elements of a map that can be drawn using this program are farm and field boundaries as well as nutrient setbacks for waterbodies.

Once the map is generated, you can copy and paste it into a Microsoft Word document to add the remaining required elements such as name and address of the client, address and tax account ID(s) of the property, names and acreage of each field, and road names (if not already visible). An example of a map can be found on the ANMP website under Software -> QGIS -> QGIS Help Guides and Templates:

https://extension.umd.edu/anmp/software/qgis-help-guides-and-templates.

\*\*If P-Risk assessments are needed for the farm, please use QGIS instead. QGIS has the ability to measure slope and distance for determining soil loss while Google Earth Pro does not.

#### Contents


In this document, you will find instructions for:

- Downloading Google Earth Pro
- Locating and mapping the property of interest
- Mapping water features and their required buffer zones

#### Downloading Google Earth Pro

#### Instructions

Step	Action
1	Download Google Earth Pro here:
	https://www.google.com/earth/download/gep/agree.html.
	In your "Downloads" folder, click on the
	GoogleEarthProSetup.exe file and follow prompts to install the program.
2	Open the program. Close the "Startup Tips" screen if applicable.
	<ul> <li>You can choose to turn this feature on or off near the "Close" button.</li> </ul>




# Locating and mapping the property of interest

#### Instructions

Step	Action
1	When Google Earth Pro is open, a globe or map is displayed on the right side of the screen and three boxes; Search, Places and Layers are displayed on the left.  a) In the Search box, enter the address of the property for which you will create a map. Then press return or click on "Search". An aerial view of the property will display on the right side of the screen.
	View Tools Add Help  ✓ Toolbar  ✓ Toolbar  ✓ Sidebar  Ctrl+Alt+B  Full Screen  View Size  Show Navigation  ✓ Status Bar  Grid  Ctrl+L  Overview Map  Scale Legend  ✓ Tour Guide  ✓ Atmosphere  Sun  Historical Imagery  ✓ Water Surface  Explore  Reset  Tilt  Make this my start location  Gallery  b) In the toolbar, click on "View"  -> "Reset" ->  "Tilt and  Compass". This will reset and align the aerial view. You may need to repeat this step before taking a screenshot of your finished map.  Tilt and Compass
2	Click on the arrow to the left in the "Places" box.  a) Right click on My Places, then click "Add" then "Folder" to create a folder to store this map. Give the folder the client's name, then click "OK".
3	If the client farms multiple tracts/properties you may choose to add additional folders for each tract/property within the client folder.  • Right click the client's folder, then choose "Add" and "Folder". Give the folder the tract/property name.

- 4 Right click on the tract/property folder you just created. Choose "Add" and choose "Polygon".
  - a) Give the polygon a field name/number (you may choose to include the farm name to keep things organized).
    - Within this "Google Earth Pro- New polygon" box, click on the "Style, Color" tab. Under Lines, select the line color you wish to use (white copies best) and width of the line. Select the color by clicking on the white box to the right of the word Color. This will bring up the color palette.
    - Under Area choose "outlined" from the dropdown menu.



- b) **Do Not** click "OK" or close the New Polygon box yet.
- c) Move your cursor over to the map. It will change to a square. Click around the perimeter of the field you want to outline.
- d) When finished with that field, click "OK" in the New Polygon box to close it.
- 5 Repeat step 4 for each of the fields on the farm until all fields are outlined.

Be sure to make a polygon of the entire farm to show the farm boundaries. You may want to make this a different color than field boundaries.

- As always, reset the tilt and compass of your map when you are finished making changes.
  - In the toolbar, click on "View" -> "Reset" -> "Tilt and Compass".


### Mapping water Instructions features and their required buffer zones

Step	Action
1	Determine if there are any waterbodies on or near your client's
	properties that could need nutrient application setbacks:
	<ul> <li>Use your client's knowledge</li> </ul>
	<ul> <li>Verify using Google Maps: <a href="https://maps.google.com/">https://maps.google.com/</a></li> </ul>
	<ul> <li>Use the search bar to locate the property.</li> </ul>
	<ul> <li>Light blue lines represent streams and blue</li> </ul>
	polygons represent ponds.
	Manor Woods Rd
	Hot sheat Run
	ytop <sup>eet</sup> Mayne's Tree
	<ul> <li>**Hint: Click on the "Earth" box in the lower</li> </ul>
	right corner to see if the map matches what
	you see in Google Earth Pro
	Earth
	<ul> <li>Make sure to inspect your map in Google Earth Pro as well since some waterbodies may not be outlined.</li> <li>For example:</li> </ul>
	Vou cannot see the pend in the left picture but
	You cannot see the pond in the left picture but can see it in the right picture
	? 4-

Next, you will need to add these waterbodies to your map for the specific farm you are working on. First, we'll start with any streams. Skip this step if no streams are present.

#### For streams:

a) Right click on the client's folder in the **My Places** menu. Choose "Add"-> "Path".




- b) A window will pop up labeled "Google Earth Pro New Path". Name your pathway as a stream.
  - Under the "Style, Color" tab, choose the Color you'd like for your stream (pick something different than your field and farm boundaries).
     Also set the Width to 2.0.
- c) Keeping this window open, trace the pathway of the stream by clicking along the pathway.
- d) When you are done, click "OK" in the "Google Earth Pro New Path window".

<sup>\*\*</sup>Hint: You can go back and edit properties or even the location of your stream by right clicking on the Stream in the Places menu and clicking on Properties. This will open up the Pathway window you were just viewing.


Now you should map any ponds (skip this step if none are present).

#### For Ponds:

a) Right click on the client's folder in the **My Places** menu. Choose "Add"-> "Polygon".




- b) A window will pop up labeled "Google Earth Pro New Polygon". Name your polygon as a pond.
  - Under the "Style, Color" tab, choose the Color you'd like for your pond. Keep the color the same in the Lines and Area sections. For the Area, choose "Filled+Outlined" from the dropdown menu.




- c) Keeping this window open, trace the shape of the pond by clicking along the pond edges.
- d) When you are done, click "OK" in the "Google Earth Pro New Polygon" window.

\*\*Hint: You can go back and edit properties or even the location of your pond by right clicking on the Pond Polygon in the Places menu and clicking on Properties. This will open up the Polygon window you were just viewing.


- To create buffers, you will need to save your stream and pond as .KML files. **Each will need to be done separately.** 
  - a) Right click on the shape, and click on "Save Place As..."




- b) Navigate to your client's folder on your computer.
  - o Type in a **File name**.
  - Change the Save as type to the Kml (\*.kml) type. Then click on Save.




c) Repeat step 4 for all streams and ponds.







b) A window with a map will pop up to show you the buffered pond. At the top of the window, next to "Pond" click on the blue icon to download the new KML file.



- c) Find the file (it will likely be saved in the Downloads folder on your computer) and rename it to include the farm, the pond, and the size of the buffer (for example: "PracticePondBuffer35ft").
- d) Move the file to your client's folder.
- e) Go back to the map window and close it. Back at the U. of New Hampshire website, enter 10 feet into the buffer box and click "Buffer".
- f) Repeat steps 7b 7d to save and name the file in the appropriate folder.
- 8 To load the files into Google Earth Pro:
  - a) Click on "File" -> "Open..."
  - b) Navigate to where you saved your files. Choose one of the 35' buffer files first. Click on "Open".
  - c) The file will load under Temporary Places in the My Places menu. Drag it to your client's folder under My Places.





Last Updated May 2017